



SpinFire Reader 2004 v2 Build 830 Release Notes

August 2, 2004

New Features

- **Access to all documents in the .3D Workspace**—SpinFire Reader can now view all the documents included in a .3D file. The Reader's desktop interface includes a box titled "Workspace Documents" which lists all the documents available in the file. To view a document, a user need only to click the name of the document in the list.
- **Display of 2D documents and other document formats**—2D raster image documents in a .3D file can be viewed with SpinFire Reader, along with all drawing and redlining markups those documents contain. The Reader can also display other document formats (such as PDF and Excel) that have been saved as part of the .3D file, provided that the appropriate plug-in for Internet Explorer has been installed.
- **New toolbars for the desktop interface**—Toolbars in the SpinFire Reader desktop interface give users access to commands for working with documents. Options available in the toolbar will differ depending on whether a 3D or 2D document is open.
- **New method for taking measurements**—Taking measurements in SpinFire Reader no longer involves adding measurement labels. Measurements (available only in desktop mode) now appear in a field on the right of the toolbar. Users may select the measurement in this field and copy it to their Windows clipboard. The Units menu to the right of the field lets users select a unit of measurement.
- **Read-only access to .3D files**—This version of SpinFire Reader does not allow any changes (such as measurement labels) to be saved to the .3D file. Users, however, still have the option of saving a .3D file hosted on a web page to their local computer or saving a .3D with a new name.
- **Background color and gradient commands available from the right-click menu**—In previous versions these options were set using buttons located on the interface window.

Known Issues

- **In desktop mode, refreshing the browser window reloads the file listed in the address bar (#1533)**—The file listed in the address bar will not necessarily be the same as the currently open file.
- **Turning off cross-section plane in 4 Viewport mode may cause Reader to quit (#1540)**—If a cross-section plane is enabled and the 4 Viewport mode is active, clicking a new Viewport and then right-clicking a cross-section plane handle in one of the Viewports and selecting Off will cause SpinFire Reader to quit. This issue will be addressed in the next release of SpinFire Reader.
- **File download progress indicator is missing when Reader is in plug-in mode**—This issue will be addressed in the next release of SpinFire Reader.
- **Ad banner may be missing when no Internet connection is available (#1348)**—Instead, an HTML page indicating "Page Not Found" will appear in that location. This will not affect the functionality of SpinFire Reader.
- **Refreshing the browser window in desktop mode causes a script error**—This error will not affect the functionality of SpinFire Reader.